


Inhaltsverzeichnis

1. First Steps	3
1.1 Start the client and log in to Teamcenter	3
1.2 Changing the password	5
1.3 Setting of the project context	6

1. First Steps

1.1 Start the client and log in to Teamcenter

After installing Teamcenter, the shortcuts to start the client are located in the folder „**c:\splmlocal\int00\appl\Shortcuts**“ (integration environments) or „**c:\splmlocal\prod00\appl\Shortcuts**“ in the production environment. The client is available in English and German. There is also a shortcut for the locations Germany (DE), Hungary (HU) and USA (US), because there are local servers for the Teamcenter and NX configurations.



Copy the desired shortcut to your desktop, in this example the client is in English, which uses the configuration in Germany.



Double-click to start the client.

The image shows the Siemens Teamcenter login interface. At the top left is the Siemens logo with the tagline 'Ingenuity for life'. Below it are input fields for 'Username' (containing 'jdoe'), 'Password' (masked with dots), 'Group', and 'Role'. A dropdown menu for 'Environment' is open, showing 'int02-4Tier' selected and circled in red. To the right of the dropdown is a 'Version 12.0' label. Below the input fields are 'Clear', 'Login', and 'Cancel' buttons. On the right side, there is a large teal box with the word 'Teamcenter' in white. At the bottom right, a white box contains the text 'Siemens PLM Software'. The background is a blue and green abstract graphic with a grid pattern. At the bottom left, small text reads '© 2018 Siemens Product Lifecycle Management Software Inc.'

SIEMENS
Ingenuity for life

Username: jdoe
Password:
Group:
Role:
Environment: int02-4Tier
Clear Login Cancel

Version 12.0


Teamcenter

Siemens PLM Software

© 2018 Siemens Product Lifecycle Management Software Inc.

A login dialog appears in which you have to enter your username (here jdoe) and your password. Furthermore, you can select several environments for the integration client. The int02-4Tier environment is used for testing and training purposes and does not contain any migrated data.


Optionally, you can also enter a group and role that deviates from the default group. This is generally not used, as it is easy to change the group/role at any time after logging in.



After logging in, you are in the application „My Teamcenter“ or also called „Teamcenter Navigator“. There you have a „Home“ folder in which you can store data in order to access it quickly.

1.2 Changing the password

If you have logged in to Teamcenter, you should change your initial password. Click on your name in the status bar.




In the following dialog click on the „Login“ tab and then on „Change Password“. You can now assign a new password and confirm with „OK“.

1.3 Setting of the project context


Teamcenter is configured at FFG so that parts can only be created in a „project context“. During the migration, the „EAC“ data is migrated as a Teamcenter project, i.e. there are the projects „00002 (MAG-Intern“), etc. Each user is assigned to one or more projects, the parts then receive this project assignment, which in turn controls the visibility of the parts.

Each user must or can set the project context himself from the list of possible projects.


Tip: If the following message appears when creating a part, you have not set the project context.



To set the project context, click on your name in the upper bar of the Teamcenter Navigator. In the following dialog you can select your current project under „Project“, in which you would like to work („Project context“). The generated parts then receive exactly this project assignment.



Press „OK“. The project context is now displayed in the status bar.



The project assignment of a part can be seen in the „Summary“ tab of the revision at the bottom right.

Home

X.0003.0029 MASCHINENBETT

My Worklist

Home

Mailbox

Newstuff

X.0003.0032 BEARBEITUNGSZENTRUM

X.0003.0032-View

X.0003.0032-01 BEARBEITUNGSZENTRUM

Use Cases

Create part in Teamcenter

X.0000.0002 LOCATING PLATE

X.0000.0002-00 LOCATING PLATE

Release Processes

AutoCAD

Summary

Details

Impact Analysis

Viewer

JT Preview

Process History

X.0000.0002-00 LOCATING PLATE

Overview

Document Properties

Title Block

Related Datasets

Available Revisions

Audit Logs

Cust. Lang.: EI SAP Proj.-No.: GP SAP Proj.-No.: 0

English: LOCATING PLATE Add. name English: German: AUFLAGEPLATTE Add. name German: Cust. lang.: Add. name cust. lang.: Naming Catalog ID: 270 Add. name (gen.): Dimension: Material: Standard:

Procur.Ind.: X Char. Key: E Weight: Sched. strategy: R + W Part: Rework: False Bom Usage: Standard Part: No Unit Of Measure: Factor UoI: Unit Of Issue: Factor UoM:

Class 1: Class 2: Class 3: Class 4:

Manufacturer ID: Notes GER: Manufacturer Name: Notes ENG: Mandatory Manufacturers: False Int.Info: Distributor Order Nr.: SAP Name (DE): Eng.Area: SAP Name (EN): Design Resp.: Import from: Evaluation class: After Sales Part: False Replaced By: Q-Code: Q XLO Part ID: G&L Product Line: XLO Draw. No.: G&L Shared Part (Sheffield): False

Last Release Status: No Value Owner: Doe, John Project (EAC-ID): 00002 Approved By: Last modified by: Doe, John Project (EAC owner): MAG Intern Approval Date: 15-Jul-2019 11:27 Checked-Out: Change Number: Date Modified: 15-Jul-2019 11:29 Checked Out By: Valid From: Valid Until Date: